Language Support

TOUC						
🗐 documentation					Revision 1.17, 9 <sup>th</sup> Jan 201	15
<u>Utilisation</u>	Selection	Procedure	Translation files	Locale identifiers	Language files	Process
Testing	Considerations	Help Files	License files	Program Manager	Windows shortcuts	Contact

## Language utilisation

The UPDD auxiliary programs have been written to support multiple languages and UPDD ships with a number of language files. When invoked the utility programs will automatically detect the systems locale (language setting) and switch to the appropriate language if the associated language file exist otherwise English (US) text is displayed as default.

## As of 25<sup>th</sup> Jan 2014 the UPDD version 4 language files have been frozen and a new set of language files created for UPDD 5.1.x therefore we only have the ability to add or amend text for subsequent translation in version 5.1.x.

Here as some examples of the UPDD Console in various languages:

onsole UPDD			
tionic, x-y	0	KesTuuch, KEA-E0210-	RIA O
Matériel Mode de clic Propriétés Calibrage	🐙 Traitement du bureau Whole 🔿 Connecté à Part USD	● 2010 ● 2010 ● 2010 ● 20	₩ 理点而Thole → 连接到 COM1
Elat	<ul> <li>Options du logiciel</li> <li>Détecter à nouveau les</li> <li>périphériques prêts à l'emploi</li> </ul>	t nouveau po r pšilphórique	中 加载新设备
Calibrei	🖌 Fermer 🕜 Aide 🧃 /	A propos	√ 关闭 3 帮助 i) 关于
ench		Chinese	
UPDD Console			
ptronic, x-p	U	Zyttonic, x y	0
جهال الم طريقة الشفط بالعارم مصالحات ال	کی بینین کی	۲ - ۲۹ - ۲۹ - ۲۹ ۲ - ۲۹ - ۲۹ - ۲۹ ۲ - ۲۹ - ۲۹ - ۲۹ - ۲۹ - ۲۹ - ۲۹ - ۲۹ -	🐙 画面の 全体 を操作 ➡ COM1 に接殺
الرضع	ب م اجاری وهی المعدن ارتیه کشاباد طریقة بد م 5 زمن الاطلاق	·····	

The language font should be rendered correctly on a system where the native language support matches that in UPDD. Given that UPDD auto selects the translations based on the OS language this will always be the case for normal usage.

A UPDD setting and command line parameter also exists to override the language selection and specify the actual language suite to use as described below.

#### Language selection

In normal use the language selected by the UPDD utilities is defined by the system's locale (the native language of the system). However, this can be overridden if required as described below. *It is important to understand that when overriding the language selection on a non native system it cannot be guaranteed that the language font will render correctly. An example of a badly rendered font is shown below.* 

## UPDD wide setting

If you want to view all UPDD utility programs in a different language to the locale of the system then you need to change the UPDD 'Language' setting to define the language file to be used. E.g. setting the value to DE whilst using an English system will force UPDD to use the German files.

For **UPDD version 4.1.x and above** this is held in the UPDD INI file under the [UPDD\parameters] section. You can use the 4.1.10 <u>command line interface</u> to change this setting. This Windows example "tbutils nodevice sz language JP" defaults UPDD language selection to Japanese.

#### Individual utility selection

In all UPDD version 4 and above, a command line parameter (-lang xx) can be passed to all UPDD utility programs as an

alternative way to specify the language file to be used. This is particularly useful for utilities that do not have access to the above UPDD setting, such as the UPDD install program.

In the following example, dcu –lang ko will show the UPDD Console with the Korean language:

■ UPDD 콘솔	X
Elo, Smartset 2500 IntelliTou	ch 🕐
📀 하드웨어	
🗄 클릭 모드	厚 전체 데스크탑 조정
😂 속성	📫 USB 포트 연결됨
🛄 보정	
፻፻፵፱  툴바	
[]] 상태	🛟 재로운 디바이스 추가
	😑 디바이스 제거
표 보정	✓ 닫기 ? 도움말 ↓ UPDD 정보

As discussed earlier, when using / viewing languages on a non native system the font selected for display of the languages may cause wrapping issues as shown in these two examples of the same UPDD dialog – one where the font causes issues and another where it is OK:

Russian - wrong font (English XP system)

ytronic, ZXY100	•
Аппаратное обеспечение (h)	Тип контроллера: Zytronic, ZXY100, USB
Настройка работы мыши (c)	<b>Состояние</b> : Не подключен
😂 Свойства (р)	
—————————————————————————————————————	
	🕨 инициализацию 🥖 тестовый
состояние о	
	счетчики # сетку
	οπακοκώ Κυθτροπεί
	астройки 📮 выволана

Russian – Correct font (English Windows 7 system)



## **Translation Procedure**

Starting with UPDD Version 4 it is our intention with to create, over time, a complete set of language files. The remainder of this document describes the translation procedure, language files and the methods used to create and maintain the files such that anyone with suitable knowledge can assist us in the translation process.

## **Translation files**

The UPDD auxiliary programs have been written in a cross platform development tool called QT. QT translations are held in files with .qm extensions. Each translation files is associated with a specific program in the UPDD suite, as shown below:

File	Description
dcu_xx.qm	UPDD Console Program
helpviewer_xx.qm	Help file viewer
tbcalib_xx.qm	Calibration program
updddraw_xx.qm	Test program
tbdaemon_xx.qm	Daemon process (system tray etc) – Windows only (no longer used in UPDD $5.1.x$ )
Aidaemon_xx.qm	Daemon process – generic
qt_xx.qm	QT graphics lib. Internal QT languages for standard dialogs can be created or overridden with text in this file.

The xx element of the file name relates to the system locale code use to identify the system language.

Starting with UPDD build 5.1.1248, updd now utilises a common component to detect languages and select appropriate translations.

aidaemon dcu (also used in Windows setup) helpviewer tbcalib updddraw

The module selects the 2 character language code as follows

If a code is passed as an argument to the program then that code is used and processing continues at the qm selection stage.

Otherwise if the language override setting in tbupdd.ini is set then this is used and processing continues at the qm selection stage.

Otherwise the preferred ui language is obtained using a Qt API **QLocale::uiLanguages.** Then the following logic is applied.

If the system locale (as given by **QLocale::name()**) is zh\_TW or zh\_HK then a language code of ct is used.

If the system locale (as given by **QLocale::name()**) is en\_GB then a language code of en is used, otherwise if the ui language is en translation processing is skipped and the internal US English values are used.

See <u>http://www.science.co.il/Language/Locale-Codes.asp</u> for a comprehensive list of locale codes.

## **Locale identifiers**

As and when we support a language the appropriate QT UPDD translation files will be placed in the UPDD translation FTP read only folder at <u>ftp://translate:translate@ftp3.touch-base.com/lupdate</u>. Currently the translation files held for UPDD are:

Locale	Language	Locale	Language
СН	Swiss	NL	Dutch
DE	German	SV	Swedish
ES	Spanish	DA	Danish
FR	French	AR	Arabic
JA	Japanese	CS	Czech
КО	Korean	HE	Hebrew
PT	Portuguese	$ZH(_TW) = CT (Taiwan) *$	Traditional Chinese
$ZH(_CN) = ZH (China) *$	Simplified Chinese	ZH(_HK) = CT (Hong Kong) *	Traditional Chinese
ZH(_SG) = ZH (Singapore) *	Simplified Chinese	ZH(_MO) = ZH (Macau) *	Simplified Chinese
HU	Hungarian	FI	Finnish
IT	Italian	RU	Russian
NO	Norwegian	LV	Latvian
EL	Greek, Modern	PL	Polish
TR	Turkish	EN	English (UK)

\* - Chinese systems report ZH for 2 character locale. UPDD analyses the extended 5 character code and for Taiwan and Hong Kong utilises UPDD Traditional language files CT (e.g DCU\_CT).

Additional translation files will be created as and when required.

## Language files

Translation files are processed and integrated into the UPDD production system and distributed as UPDD language files as part of the standard install. These language files will also be available from the UPDD language FTP folder at <a href="http://translate:translate@ftp3.touch-base.com/qm">http://translate@ftp3.touch-base.com/qm</a>.

#### Location

By default the .qm language files (named <module>\_<lang>.qm) are placed in the UPDD application folder. Should the files need to be located elsewhere copy the required files to the new folder location and specify the path of the folder in the QMFolder setting in the [updd\parameters] section of tbupdd.ini settings file. You can manually edit the file or use the tbutils command line interface, such as: Tbutils nodevice setting sz "QMFolder=c:\program files\updd\testqm".

If a file with a name matching that of the current module + selected language code is found then it is used.

## Translation process and submission

Should a language file not be available, or need amending, and you or your organisation is able to assist in the translation process please note the following procedures to submit translated text.

- Download the QT translation tool (<u>linguist.exe</u> click to initiate download) and its dll (<u>qt-mt336.dll</u> click to initiate download) to a folder on a Windows system. They can also be downloaded from the FTP site <u>ftp://translate:translate@ftp3.touch-base.com/lupdate</u>.
- 2) Copy the \*.qm files (from the same FTP location as 1 above) appropriate to your language to the same folder.



It is important that you only copy files for languages you have agreed with Touch-Base. Files for other languages may be in translation by other parties and your changes might be lost.

If the translation file does not exist <u>contact Touch-Base</u> who will create the files and email you when they are ready to be accessed.

If you do not know the locale of your target system user the –langtest parameter (to any translatable UPDD module) to display the locale info, as shown in the following Mac OS X example against the tbcalib module.

command - /Applications/Utilities/UPDD\ Calibration.app/Contents/MacOS/tbcalib -langtest

-	Module: tbcalib
1)	UILanguage: fr
~	locale name: fr_FR
	qmFolder: /Library/Application Support/UPDD
	language: fr
	OK

3) Open each of the translation files in turn using the translation tool (linguist.exe program) and translate the listed text, as shown in the example dialog below:

0			× Done	Source text	🗢 🗅 🎙 🖓 🗳	S See See See See See See See See See S	2
Done       Context       Ite         @default       AddDevice         @default       Ite         AddDevice       Ite         @default       Ite         @defa		tems 0/12 1/65 0/2 0/8 0/34 0/7 0/5 0/2 0/109 0/4 0/45 0/5 0/2 0/1 0/18 0/2 0/18 0/2 0/2 0/2 0/2	Source Cancel Transla Annulati	Add a new devic OK Cancel Help <b>Enter a name <b>and select th Monitor 1 Monitor 2 Monitor 3 Monitor 4</b></b>	e e to identify the new device< e monitor or desktop area 1</td <td>Annulation /b&gt; &gt;&gt;</td> <td></td>	Annulation /b> >>	
<u> </u>	ToolbarSettings ZYBar Zytronic ZytronicSensorTest	0/15 0/3 0/17 0/4	× Phras	es and guesses: rce phrase	Translation	Definition	

In this example, the French UPDD Console program has been opened (dcu\_fr.qm) and in the AddDevice section the word 'Cancel' has been translated to 'Annulation' and the entry has been marked as translated (by clicking on the question mark preceding the entry).

The left hand column shows the number of translations within the module and the number completed. As each translation is made click on the ? icon next to the translation which will change to a  $\checkmark$  icon to show the translation has been made. This visual registration of the translations is important to show the translation progress and the modules with outstanding translations entries. It also allows for easy identification of the entries that require translation. If an exclamation mark ? is shown instead of the green tick the status line at the bottom of the translation dialog will indicate the issue with the translation. E.g. Translation does not end with the same punctuation as the source text.

In the following example there are two outstanding translations in the Install module. All other modules are complete:

0			🕺 🗇 🗳 🗢 💠 🏞 🖓 🗶 !? 🦏	, <b>N</b> ?
		×	Done Source text	Translation
Done	Context	Items	COM10	COM10
1	@default	12/12	COM12	COM12
1	AddDevice	66/66	COM13	COM13
1	GetKey	2/2	COM14	COM14
1	History	8/8	✓ COM15	COM15
8	Install	33/35	COM16	COM16
1	Install2	7/7	✓ COM17	COM17
1	KeyCode	5/5	✓ COM18	COM18
1	License	2/2	🖌 СОМ19	COM19
1	MainDialog	169/169	COM20	COM20
1	MessageBox	4/4	This program will install the Universal Pointer Device Driver softwar.	
1	ModifyDevice	45/45	2 COM11	COM11
1	PenWidth	5/5		< i.
1	PickList	2/2	Source text	
1	QWidget	1/1	SUBJECT CAL	
1	RenameDevice	18/18	This program will install the Universal Pointer Device Driver software on your	computer.(new
1	SerialPort Settings	39/39	line)	
1	SupportInfo	2/2	(new line)	
1	ToolbarCell Settings	90/90	USB controllers will be detected automatically by the install process and do n	ot need to be
1	ToolbarSettings	15/15	selected. Senal controllers need to be selected now or after the software has	been
1	ZYBar	3/3	III ISLOHOU. (new line)	
1	Zytronic	12/12	Click "Install" to proceed, or "Cancel" if you do not wish to install the softwar	e at this time.
1	Zytronic Sensor Test	4/4		a na a na ang ta
			Tenalation	100

Note that in the above translation the system is showing where a new line (new line) is embedded in the text. Where these hidden characters are shown please ensure the translated text contains that same formatting e.g (new line) should have a new line in the text, (sp) should have a space etc.

In the example below the translated text has a space at the beginning and the end:

			<b>×</b>	×	Done	Source text
Done	Context	Items			1	Whole
	CalibDlg		7/7		1	Desktop
1	EepromUpdate		2/2		1	on
1	QWidget		6/6		1	Please touch the poin
					1	Please touch the cent
					1	Please touch the tip o
				F		
				l s	ource	text
					sp)ON(sp)	
				Шт	ransla	tion
					Включе	но
1						

A guide to the translation procedure is available at <u>http://doc.trolltech.com/3.1/linguist-manual.html</u> which links to a <u>full</u> <u>description of the translation tool</u>.

**VERY VERY IMPORTANT NOTE1:** Only translate entries that appear to be plain text. Leave control characters (e.g. %2, < or &gt or <b> or </b> or , <font color = "#4a7ac9"> etc) **untranslated**. Placement holders, such as xxx yyy 9999, nn:nn, xx:xx:xx should be left alone.

i.e. German example

NOT results in	<zeichen farbe="#4a7ac9"><b>Priorität</b></zeichen>						
	Mode Sperre O						
	Auslösezeit 5 🔷 🛧 🔸						
was becomes	<b>ChangesVeränderungen </b>						

ΝΟΤ

<b>Veränderungen</b>

**VERY VERY IMPORTANT NOTE2:** Do not translate com port names as these names are used to reserve the serial port for use by the driver. i.e. COM1 must say COM1 etc.

4) In the calibration program, during calibration, we display the name of the controller being calibrated and also show the desktop segment. As an example, in English this would be shown as "Touch Controller X on Monitor 2" This sentence comes from the text strings (found in TBcalib\_xx.ts, section QWidget):

%1 on Monitor 1 %1 on Monitor 2 etc

where %1 will be replaced with the controller name but can be anywhere in the translation. These strings should be translated so that the sentence reads correctly in the given language.

- 5) Some text does not need to be translated as in a very few cases there is customer related entries which are used in special OEM builds of our software: Examples of this text is; Egan PowerX, Easiteach Teamboard, Zytronics. If there is text that you are unsure of email us and we will advise further.
- 6) Some text associated with controls ends with 3 dots ... This has a specific meaning in the Windows user interface guidelines and as such should be retained in the translations.
- 7) If an exclamation mark ( ) is shown it often indicates a different punctuation, especially if questions marks are added. This behaviour can be configured in menu option "validation -> ending punctuation".

# If you find any unusual entries or translated text that you disagree with please discuss this with Touch-Base. Do not change without Touch-Base's agreement.

a) Going to URL <u>http://upload.touch-base.com</u> and dragging the files from your system to the drop zone on the page. **or** 

b) Copy the ftp path <a href="http://translate:translate@ftp3.touch-base.com/lupdatereturn">http://translate:translate@ftp3.touch-base.com/lupdatereturn</a> into Windows Explorer and drag the files to the folder.

Please inform us that new translation files are ready to process and we will integrate the new files into the UPDD software.

**Important note**: you MUST not apply further changes to the translation files after returning them to Touch-Base. You should wait for acknowledgement that your changes have been processed then start again at stage 1 above. \*\*\* *failure to follow this process will lead to loss of changes*.

9) Once processed you may download the language (\*.qm) files from <u>ftp://translate@ftp3.touch-base.com/qm</u> and copy to your UPDD application folder. These files will be used automatically when a language file that matches the OS locale is found. The most up-to-date language files will be applied to production released software.

The translation process is iterative. After each translation cycle the display and operation of the software will be reviewed and further translations may be required as a result.

## Testing

The updated translation file will be processed by Touch-Base and made available for testing. Having downloaded the updated language file you can run up the appropriate UPDD utility and view the new translations. Prior to submitting the updated translation files you can create a language file using the program <u>lrelease.exe</u> passing the names of the .ts and .qm files;

e.g ' Irelease dcu-cs.ts dcu-cs.qm'.

## Considerations

The UPDD dialogs are initially laid out with the English text and therefore the white space available for translated text needs to take into consideration the space initially allocated. Generally speaking text will wrap if it is longer than the allocated space and will not always be readable if the text exceeds the available height of the allocated area should it wrap.

When considering the translations to use you also need to consider if the system can be configured to utilize large font sizes and try and cater for the range of dialog fonts. For example, in Windows 7, the end user can specify text size to use in the Display Properties and it is important to test the translations in all the available options.

🕒 🖉 🖉 🧠 Appearance and	Personaliza + Display + + + Search Control Panel
Control Panel Home Adjust resolution Calibrate color Change display settings Adjust ClearType text Set custom text size (DPI)	Make it easier to read what's on your screen You can change the size of text and other items on your screen by choosing one of these options. To temporarily enlarge just part of the screen, use the Magnifier tool.  Smaller - 100% (default) Preview Medium - 125% Larger - 150%
See also Personalization Devices and Printers	Apply

Where display issues are seen it may require the translation to be adjusted or we may be able to increase the area available for the text display.

#### Help Files

UPDD drivers are supplied with on-line help files. Custom or translated help files can be created for distribution with our software if required. The <u>Help file document</u> describes the help system and the files used.

These files should be reproduced in the required language and send to us for inclusion in the software. We use a cross platform help viewer, called helpviewer, to view the files and this is delivered as part of the UPDD software. To test the appearance of the completed help file use 'helpviewer [filename]'. The help viewer may not handle all aspects of the HTML language so do not use advance features in the help files – keep it simple!

## Help file images

The help file images, in the supplied English help files, are held in a sub-folder called images. Listing the images sub folder in UPDD will show all the images used and their file names. The path to these images as held in the help file will be:

src="images/[imagefile].png"></span></b> e.g. src="images/calibration-style.png"></span></b>

If you create new language help files you should also create the same image files for the designated language. The directory listing example below shows the list of both English and Korean images. The Korean images have the '-ko' file extension. To create a new set of images copy the English image file to the required language image file. E.g. console\_calibration.png becomes console\_calibration-JP.png for create a Japanese file. You then replace the image with the Japanese version, cut from the UPDD dialogs.

Address 🛅 C:\Program Files\UPDD\images					💌 🄁 (
Folders	×	Name 🔺	Size	Туре	Date Modified
🖃 🗀 UPDD	~	Console_calibration.PNG	1 KB	PNG Image	17/03/2008 19:45
images	_	Console_calibration-ko.png	2 KB	PNG Image	17/03/2008 19:45
		Console_clickmode.PNG	1 KB	PNG Image	17/03/2008 19:45
		Console_clickmode-ko.png	2 KB	PNG Image	17/03/2008 19:45
		Console_functions.PNG	7 KB	PNG Image	17/03/2008 19:45
		Console_functions-ko.png	4 KB	PNG Image	17/03/2008 19:45
		Console_hardware.PNG	2 KB	PNG Image	17/03/2008 19:45
		Console_hardware-ko.png	2 KB	PNG Image	17/03/2008 19:45
		Console_properties.PNG	1 KB	PNG Image	17/03/2008 19:45
		Console_properties-ko.png	2 KB	PNG Image	17/03/2008 19:45
		ClickMode-visual.PNG	1 KB	PNG Image	17/03/2008 19:45
	~	DickMode-visual-image.PNG	3 KB	PNG Image	17/03/2008 19:45

#### Replacing images in the help file

When replacing existing images the easiest and quickest way is to load the file in a text editor, say Notepad, use Find to locate the image name in the file, say calibration-style.png, and modify the name to add the language notation, e.g. calibration-stylejp.png

#### Create and add new images

Should you need to create and add new images into the help file it is important you abide by the following rules: accent

#### Images should be held in an 'image' sub folder under the help file folder.

This is a requirement of our source control, production system and UPDD file structure:

#### The images must be referenced as external files and not embedded in the file.

For example, if using Microsoft Word to create the file use the 'Link to File' option when inserting an image, as shown below:

	Insert Picture			? 🔀	
<u>General</u> ¤ <u>Hardware</u> ¤ <u>Cli</u>	Look in:	🛅 images	💽 🚱 * 🔰 🔍 🗙 📷 📰 * Tools *		
The·calibration·dialog·is·used·to·se ¤ Function¤	My Recent Documents	calibrate.png calibrate.add.png calibrate-add.png calibrate-margin.png calibrate-points.png calibrate-remove.png calibrate-remove.png calibration-beeps.png calibration-check.png calibration-confirm.png calibration-confirm	dickmode-test.png     ClickMode-visual.PNG     ClickMode-visual-image.PNG     console.PNG     console_calibration.PNG     console_calibration.PNG     console_clickmode.PNG     console_functions.PNG     console_functions.PNG     console_hardware.PNG	Event-Selector-( firmware-zy-fr.p) firmware-zy-fv.p firmware-zy-gtk. firmware-zy-gtk. firmware-zy-se.p firmware-zy-st.p	
Style Normal 💟	My Documents My Computer	calibration-style.png calibration-timeout.png calibration-transparent.png ClickMode-Dropdown.PNG clickmode-ist.PNG clickmode-mouse-settings.png clickmode-silent.png clickmode-s	console_properties.PNG console_toolbars.PNG console_toolbars.PNG console-full.png console-history.PNG event-selector.png Event-Selector.classic-Left.png	firmware-zy-thsi firmware-zy-ts.p hardware-add.P hardware-conne hardware-conne hardware-firmwa hardware-firmwa hardware-handli	
🕂 Add a new style	My Network Places	File name:       Files of type:       All Pictures (*.emf;*	.wmf;*.jpg;*.jpeg;*.jfif;*.jpe;*.png;	Ingert V Ingert Link to File	

#### The image file paths are held as relative paths and not absolute paths

Once the file is created and all images have been embedded it is important that the image path in the HTML file is a relative path to the Images folder **and not** an absolute path. One way to check this is to load the file in a text editor, locate the image and see the path used.

In this example, we have opened up the .htm file in NotePad and located the image, which is being held as an absolute path:



This is edited to make it a relative path and the file is saved. Therefore in the above example:

src="../../../TBA/config/files/LATEST/help/images/calibration-style.png"></span></b>
becomes
src="images/calibration-style.png"></span></b>

To test that the images are ok, place the help files and images on a 'new' system with the helpview program and run up each help file in turn: e.g.

C:\helptest (.htm files) C:\helptest\images (images)

If the image is not seen in the file then the path is not pointing to the image folder and needs updating. Once all files load OK and ALL images are displayed correctly from the image path send all the files to us for inclusion.

## **Licence Files**

UPDD license details are displayed from the UPDD Console, About Box, View License option. This license is displayed in English unless the appropriate language licence file exists. To create a licence file in a different language copy the licence file <u>licence</u><u>en.txt</u> in the UPDD application to the appropriate language file (e.g. licence-ko.txt for Korean) or download the text from <u>here</u>, add the translations using a NotePad type tool and submit the update file to Touch-Base.

In some cases (such as Japanese) the control used to display the license text has failed to reliably find the string length of the file and not all the text has been displayed. Should this occur on any translated licenses you can use the marker <EOF> which the control can identify as the end of the text and display up to that point.

## **Program Manager menu entries**

The program Manager menu entries are defined in a text file called menuv4xx.txt where the xx element of the file name relates to the system locale code use to identify the system language.

The Program Manager menu entries appear as follows on an English system:

🖬 UPDD 🔸	💐 Settings
	🖾 Calibrate
	🏷 Event Selector
	🛅 Test

The text is taken from the menuv4xx.txt file. The format of the English file is as follows:

tbalt.exe;Event Selector;;0;1
updddraw.exe;Test;/test;0;1
dcu.exe;Settings;;0;1
tbcalib.exe;Calibrate;/all;0;1

To create a locale menu files perform the following steps:

- 1) Create a file using notepad called menuv4xx.txt where xx is the system locale, e.g. ja = Japanese
- 2) Copy the above 4 lines and paste them into the .txt file
- 3) Translate the 2<sup>nd</sup> element of each line, as highlighted in bold above.
  4) Save the file as ANSI

Save the file as ANSI				
File name:	menuv4jp.txt	~	Save	
Save as type:	Text Documents (*.txt)	~	Cancel	
Encoding:	ANSI	~		

5) Email the file to language co-coordinator Gary Allitt at gary@touch-base.com

Example file after translation, in the case to German:

tbalt.exe; Maustastenauswahl;;0;1
updddraw.exe; <b>Test</b> ;/test;0;1
dcu.exe; <b>Einstellungen</b> ;;0;1
tbcalib.exe;Kalibration;/all;0;1

### Selecting languages

### System

#### Windows

Since Windows 2000 the operating system can support a number of languages and keyboard layouts as listed at <a href="http://support.microsoft.com/?kbid=292246">http://support.microsoft.com/?kbid=292246</a>. The same article describes how to install and utilise the language utilities via the Control Panel, Regional and Language option.

If the Language bar is enabled in the task bar it can be used to switch languages, as shown below.



This allows for various languages to be tested with the same keyboard layout and may be of use when testing.

When testing/viewing languages on a fixed locale system it may be necessary to have installed supplemental language support as shown:

egional and Language	Regional Options Languages Advanced				
	Text services and input languages To view or change the languages and methods you can use to enter text, click Details.				
	Supplemental language support				
	select the appropriate check box below.				
	✓ Install files for complex script and right to left languages (including Thai)				
	Install files for East Asian languages				

#### Mac OS X

The System Preferences, International dialog can be used to specify the system language to use in application menus and dialogs, as shown below:

	Interna	ational
Languages:	Language Form	ats Input Menu
English	Dr	ag languages into the order you
Français	dia	alogs, and sorting.
日本語 Deutsch	C	Edit List
Español	<u> </u>	Changes take effect in the Finder the next
Italiano		applications the next time you open them.





## Contact

For further information or technical assistance please email the technical support team at <u>technical@touch-base.com</u> and the language co-coordinator Gary Allitt at <u>gary@touch-base.com</u>.